Microsoft Mobile Device - Android - E-Mail Set Up Instructions

If you don't have your email account set up yet, log-in to our Ticket System and submit a "New Ticket" asking us to set up a new email account. We will respond to your Ticket with the Username and Password.

You may log-in to our Ticket System here: https://www.clearimaging.com/client-support

.....

Instructions for Adding an Email Account in: Mobile Device - Android

Steps

- 1. Open Windows Mail.
- 2. Select "Add Account".



3. Choose "Other Account".

	×
Choose an account	
Outlook.com Outlook.com, Live.com, Hotmail, MSN	
Exchange Exchange, Office 365	
Coogle	
Yahoo! Mail	
iCloud	
Other account POP, IMAP	
🛱 Advanced setup	
Close	L

4. Enter your **Email address** and **Password**. (If you've forgotten your password, we can reset it for you)

• Click "Sign-in".

×
Other account
Email address
name@example.com
Password
•••••
We'll save this information, so you don't have to sign in every
time.
Cancel Sign-in

5. Continuously click on "**Sign-in**" until the option changes to "Advanced."

	×
Other account	
Email address	
name@example.com	
Password	
•••••	
We couldn't find info for that account. Make sure that the email address is correct and then try again.	
To add account info manually, select Advanced.	
Cancel	ר
Cancer Advanced	J

- 6. Enter the Account Information.
 - Incoming email server starts with **mail**., followed by your domain name (example: mail.my-domain.com)
 - Account type is IMAP4.
 - User name is the full email address.
 - Password is your mailbox password.
 - Outgoing (SMTP) mail server starts with mail., followed by your domain name (example: mail.my-domain.com)
 - Check all blocks.
 - Click "Sign-in".

×
Internet email account
Account name
Example
Your name
Name Sumame
We'll send your messages using this name.
Incoming email server
mail.example.com
Account type
IMAP4 ~
User name
name@example.com
Examples: kevinc, kevinc@contoso.com, domain\kevinc
Password
•••••
Outgoing (SMTP) email server
mail.example.com ×
Outgoing server requires authentication
Use the same user name and password for sending email
Require SSL for incoming email
Require SSL for outgoing email
Cancel Sign-in

- 7. You're all set!
 - Note: In some cases, **mail.domain** might not work. In such instances, you'll need to use the server name instead. (contact us for your server name)